

Installation Instructions

(SMARTcart 1.0)

System Requirements:

1. A Windows operating system (98, NT 4 w/ service pack 6, ME, 2000, or XP).
2. The Microsoft .NET framework. This allows you to run all .NET applications, including SMARTcart. The installer (dotnetfx.exe) can be downloaded from Microsoft.
3. A relatively quick computer. SMARTcart will run on slower units, but I recommend at least a Pentium 3 CPU running at 1 GHz clock speed. RAM requirements are minimal – almost any computer that meets the recommended CPU speed will be sufficient.
4. 12 Megabytes of hard disk space for SMARTcart, and about 25 Megabytes of hard disk space for the .NET framework, if it isn't already installed on your computer.
5. A mouse or other pointing device that you are familiar with, as long as it supports right clicks as well as left clicks.
6. A monitor resolution of 1024x768 is optimal. Lesser resolutions are not supported, and higher resolutions might result in small type that is difficult to read.
7. Administrative privileges on your computer.

Instructions:

1. If you are certain that the .NET framework is already installed on your computer, proceed to step 4. Otherwise, proceed to step 2.
2. On the SMARTcart Download page, click the .NET Framework link. Download the version of .NET Framework that you need. Choose to save the file to your computer when prompted – the Desktop is as good a place as any to save this file.
3. After it has downloaded, double-click the .NET Framework installer (dotnetfx.exe), and follow any instructions that appear.
4. On the SMARTcart Download page, click the SMARTcart 1.0 link. Choose to save the file to your computer when prompted – again, the Desktop is as good a place as any to save this file.
5. Run the sc1.0.exe file to decompress.
6. After decompressing, open the folder named sc1.0 that resulted from the decompression of sc1.0.exe. Double-click on the SMARTcart installer (SMARTcart 1.0.msi or Setup.exe), and follow any instructions that appear. Most users should be able to hit the Next button repeatedly, accepting all default installation options.
7. Once SMARTcart has been installed, launch it by selecting the SMARTcart 1.0 icon that appears in the Programs section of the Start menu.